

Geonautics Windows 98 Driver Installation Procedure Document

Project Name:	Geonautics USB Project
Document Title:	Windows 98 Driver Installation Procedure
Creation Date:	27-June-2003
Revision:	02-September-2003
Project Company:	Geonautics

Contents

Contents.....i

List of Figuresi

1. Driver Installation Procedure.....2

List of Figures

Figure 1.1. Wizard Opening Screen2

Figure 1.2. Wizard Driver Main Options Screen.....3

Figure 1.3. Wizard Driver Search Locations Screen.....3

Figure 1.4. Wizard Driver Search Results Screen4

Figure 1.5. Wizard Completion Screen.....4

1. Driver Installation Procedure

1. Place the Whisper installation CD in the computer's CD-ROM drive. (Cancel the Whisper program auto-install if the Whisper software has already been installed.)
2. Plug the USB cable into the computer. The '*Add New Hardware Wizard*' will be activated which is searching for '*Geonautics Dongle I*'.



Figure 1.1. Wizard Opening Screen

3. Click the '*Next >*' button.
A new wizard window will appear asking '*What do you want Windows to do?*'



Figure 1.2. Wizard Driver Main Options Screen

4. Select the 'Search for the best driver for your device (Recommended)' option and click the 'Next >' button.

A new wizard window will appear asking you to select possible search locations for the device driver:



Figure 1.3. Wizard Driver Search Locations Screen

5. Tick the 'Specify a location:' option and click the 'Browse...' button.
6. Select the Drivers directory on the CD-ROM drive and click the 'OK' button. The drop down box under the 'Specify a location' option will now display 'D:\Drivers'.

7. Press the 'Next >' button. A confirmation window displaying the 'Geonautics Dongle I Device' and location of the driver as 'D:\Drivers\Geonau~2.inf' will now be visible.



Figure 1.4. Wizard Driver Search Results Screen

8. Press the 'Next >' button.

The driver will now start installing. A final window will be displayed with 'Geonautics Dongle I Device' clearly written at its top. The window will state that 'Windows has finished installing the software that your new hardware device requires'.



Figure 1.5. Wizard Completion Screen

9. Press the 'Finish' button. The appropriate USB driver will now be installed.